Adobe® Customer Support

Questions to Ask Your Printer

To get the best results from four-color separations in Adobe® Photoshop, it is important to maintain a dialogue with the different agencies involved in getting the job printed. This may involve talking with the professionals at a color house for scans, at a service bureau for produc-ing film, and finally, at a print shop for printing the job on-press.

Of all these relationships, the dialogue with your printer is the most crucial. To begin the search for a good print shop, you should consult with several printers and tour their facilities. When you take a tour, ask to see printed samples of their work and spec sheets for their equipment. Many good printers provide information geared to working with desktop files. Be sure to find out about their printing press capabilities.

When you pick a printer and are ready to start working on a project, do not hesitate to ask any questions. Asking the right questions helps you to establish a good rapport with the printer, can avoid surprises, and build confidence about producing good separations.

The following sections detail the most important information you need from your printer to produce good color separations in Adobe Photoshop:

- The press's ability to handle screen frequencies
- Press conditions and potential dot gain
- Method for generating black separation plates
- Ink limitations of the press and the ink density of the black plate
- The printer's role in producing film

Your printer may also be able to guide you in selecting and modifying images that print well, and perhaps can recommend a color house for high-end scans.

SCREEN FREQUENCY AND IMAGE RESOLUTION

When first talking with your printer, determine the screen frequency potential of the press. The screen frequency may vary depending on the plates. Also, a higher screen frequency may be more expensive. The screen frequency directly affects the resolution of the scanned image in Adobe Photoshop. In general, the image resolution needs to be 1.5 to 2 times the screen frequency at which the file is printed. For example, if the press can support a 150-line screen, you won't need an image resolution greater than 300 pixels per inch (ppi). A higher image resolution won't yield significantly better results, but generates a much larger file size. On the other hand, a lower resolution for your image may create a file that looks blockish, or pixelated, when printed.



For more information about issues related to scanning, see the technical note, "Scanning Basics," and the Adobe Photoshop User Guide.

DOT GAIN ON PRESS

Be sure to ask how much dot gain the printer experiences on-press for a given paper stock. Ask how much dot gain is expected on-press from the film stage to press sheet in the midtones. Many printers will tell you the amount of dot gain expected from the proof stage to the press sheet, but this is an incorrect value to use in Adobe Photoshop.

In general, coated stock registers a dot gain of 18 percent to 25 percent in the midtones. Dot gain for uncoated stock and newsprint varies from 30 percent to 40 percent. Because midtones register the greatest amount of gain on-press, Adobe Photoshop uses the gain in the midtones as a good indication of the gain that occurs over the rest of the image. If your printer is unsure of the dot gain value, use the default values provided for each type of paper stock in the Printing Inks Setup dialog box.

GENERATING THE BLACK SEPARATION PLATE

Adobe Photoshop offers two ways to generate the black separation plate: Undercolor Removal (UCR) and Gray Component Replacement (GCR). The options appear in the Separation Setup dialog box.

The difference between the two methods affects mainly the black plate. GCR generates black throughout the image, beginning in the highlights. UCR generates black mainly in the 3/4-tones and in the black part of the image, thus holding shadow detail better. See how the two methods distribute black ink by observing the black in the Gray Ramp when you choose either GCR or UCR. (Notice also that the supporting C, M, and Y are adjusted.)

For best results, choose GCR or UCR, depending on which method the print shop has more experience and is more comfortable. Many printers are more comfortable with UCR. For more information about UCR and GCR, refer to the Adobe Photoshop User Guide.

INK LIMITS

Also ask your printer about the total ink limit the press can support and the total ink density used for the black plate. Enter this information in the Separation Setup dialog box. Many small to medium-sized print shops may not be able to provide this information because they may not have had to configure it. If you are unsure, use the default values.

THE PRINTER'S ROLE IN PRODUCING FILM

A close working relationship with your printer in producing film can save many headaches as well as wasted time and money. Ask your printer what role the print shop will play in producing film. Pick a printer who assumes this function in-house or who is willing to work closely with your imaging house or service bureau.



Adobe, the Adobe logo, Adobe Photoshop, are trademarks of Adobe Systems Incorporated. Macintosh is a registered trademark of Apple Computer, Inc. Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. All other trademarks are the property of their respective owners.

© 1996 Adobe Systems Incorporated. All rights reserved.